CONFIGURATION GUIDES › DOCKER

Applicare deployed in a Docker container with Derby database

Applicare 10.0 · Updated February 4, 2025 · docker, singleagent · **Pending technical review**

Pre Requisite: Make sure docker is installed before following the below steps.


Windows:

Step 1: Launch PowerShell as an Administrator and execute the following command.

```bat
 curl -o start_applicare.bat https://applicarepatch.blob.core.windows.net/java-file/start_applicare.bat; .\start_applicare.bat
```

Step 2: Then enter the **server IP** when prompted.

server IP -> The IP of the machine where docker is running.



Step 3: After few minutes you can access the Applicare console in the browser.

```text
http://<server IP>:8880/applicare
```

server IP ->The IP of the machine where docker is running.

Linux:

Step 1: Download the file "**start_applicare_linux.sh**" using either **curl** or **wget**, depending on your preference.

Curl:

```bash
curl -o start_applicare_linux.sh https://applicarepatch.blob.core.windows.net/java-file/start_applicare_linux.sh
```


Or

Wget:

```bash
wget https://applicarepatch.blob.core.windows.net/java-file/start_applicare_linux.sh
```

Step 2: After download the file give the execute permission for that file. Then run the file in putty season, then enter the **server IP** when prompted.

server IP -> The IP of the machine where docker is running.



Step 3: After few minutes can access the console in the browser.

```
TEXT
http://<server IP>:8880/applicare
```

server IP ->The IP of the machine where docker is running.

Mac:

Step 1: Download the file "**start_applicare_mac.sh**" using either **curl** or **wget**, depending on your preference.

Curl:

```
BASH
curl -o start_applicare_mac.sh
https://applicare.blob.core.windows.net/docker/start_applicare_mac.sh
```


Or

Wget:

```
BASH
wget https://applicare.blob.core.windows.net/docker/start_applicare_mac.sh
```

Step 2: After download the file give the execute permission for that file. Then run the file in terminal window, Then enter the **server IP** when prompted.

server IP -> The IP of the machine where docker is running.



Step 3: After few minutes can access the console in the browser.

```
TEXT
http://<server IP>:8880/applicare
```

server IP ->The IP of the machine where docker is running.